

Oracle RAC on VMware vSphere Deployment Guide

July 2011

© 2011 VMware, Inc. All rights reserved. This product is protected by U.S. and international copyright and intellectual property laws. This product is covered by one or more patents listed at http://www.vmware.com/download/patents.html.

VMware is a registered trademark or trademark of VMware, Inc. in the United States and/or other jurisdictions. All other marks and names mentioned herein may be trademarks of their respective companies.

VMware, Inc. 3401 Hillview Ave Palo Alto, CA 94304 www.vmware.com

> © 2011 VMware, Inc. All rights reserved. Page 2 of 46

Contents

2. Infrastructure Environment	1.	Introduction5
2.2 Software Environment. 6 2.3 VMware Virtual Machines. 6 2.4 Virtual Disk Layout. 7 2.5 Oracle RAC Database Environment. 8 2.6 Network Configuration 8 2.7 Physical Architecture 10 Logical Architecture 11 11 3. Overview of Deployment Steps 12 4. Configure NTP Client on all ESX Hosts 13 5. Prepare a Virtual Machine for the First RAC Node 15 5.1 Create a Virtual Machine 15 5.2 Add Two NICs 15 5.3 Add CRS and Voting Disk 16 5.4 Install the Guest Operating System 20 5.5 Install VMware Tools 21 5.6 Time Keeping with Linux Guest Operation System 22 6. Prepare Subsequent Virtual Machine/RAC Node 23 6.1 Clone the First Virtual Machine/RAC Node 23 6.2 Change the Hostname and Assign an IP Address 23 6.3 Configure CSR and Voting Disks 24 <	2.	Infrastructure Environment6
2.3 VMware Virtual Machines 6 2.4 Virtual Disk Layout 7 2.5 Oracle RAC Database Environment 8 2.6 Network Configuration 8 2.7 Physical Architecture 10 Logical Architecture 11 11 3. Overview of Deployment Steps 12 4. Configure NTP Client on all ESX Hosts 13 5. Prepare a Virtual Machine for the First RAC Node 15 5.1 Create a Virtual Machine 15 5.2 Add Two NICs 15 5.3 Add CRS and Voting Disk 16 5.4 Install the Guest Operating System 20 5.5 Install the Guest Operating System 22 6. Prepare Subsequent Virtual Machine/RAC Node 23 6.1 Clone the First Virtual Machine/RAC Node 23 6.3 Configure CSR and Voting Disks 24 6.4 Format the Added Disks Using fdisk 26 7. Install Oracle Grid Infrastructure Installation 29		2.1 Hardware6
2.4 Virtual Disk Layout 7 2.5 Oracle RAC Database Environment 8 2.6 Network Configuration 8 2.7 Physical Architecture 10 Logical Architecture 11 11 3. Overview of Deployment Steps 12 4. Configure NTP Client on all ESX Hosts 13 5. Prepare a Virtual Machine for the First RAC Node 15 5.1 Create a Virtual Machine 15 5.2 Add Two NICs 15 5.3 Add CRS and Voting Disk 16 5.4 Install the Guest Operating System 20 5.5 Install VMware Tools 21 5.6 Time Keeping with Linux Guest Operation System 22 6. Prepare Subsequent Virtual Machines/RAC Nodes 23 6.1 Clone the First Virtual Machine/RAC Node 23 6.2 Change the Hostname and Assign an IP Address 23 6.3 Configure CSR and Voting Disks 24 6.4 Format the Added Disks Using fdisk. 26 7. Install Oracle Grid Infrastructure Installation		2.2 Software Environment
2.5 Oracle RAC Database Environment 8 2.6 Network Configuration 8 2.7 Physical Architecture 10 Logical Architecture 11 11 3. Overview of Deployment Steps 12 4. Configure NTP Client on all ESX Hosts 13 5. Prepare a Virtual Machine for the First RAC Node 15 5.1 Create a Virtual Machine 15 5.2 Add Two NICs 15 5.3 Add CRS and Voting Disk 16 5.4 Install the Guest Operating System 20 5.5 Install VMware Tools 21 5.6 Time Keeping with Linux Guest Operation System 22 6. Prepare Subsequent Virtual Machine/RAC Node 23 6.1 Clone the First Virtual Machine/RAC Node 23 6.2 Change the Hostname and Assign an IP Address 23 6.3 Configure CSR and Voting Disks 24 6.4 Format the Added Disks Using fdisk. 26 7. Install Oracle Grid Infrastructure 27 8. Verify the Grid Infrastructure Installation <td></td> <td>2.3 VMware Virtual Machines6</td>		2.3 VMware Virtual Machines6
2.6 Network Configuration 8 2.7 Physical Architecture 10 Logical Architecture 11 3. Overview of Deployment Steps 12 4. Configure NTP Client on all ESX Hosts 13 5. Prepare a Virtual Machine for the First RAC Node 15 5.1 Create a Virtual Machine 15 5.2 Add Two NICs 15 5.3 Add CRS and Voting Disk 16 5.4 Install the Guest Operating System 20 5.5 Install VMware Tools 21 5.6 Time Keeping with Linux Guest Operation System 22 6. Prepare Subsequent Virtual Machines/RAC Nodes 23 6.1 Clone the First Virtual Machine/RAC Node 23 6.2 Change the Hostname and Assign an IP Address 23 6.3 Configure CSR and Voting Disks 24 6.4 Format the Added Disks Using fdisk. 26 7. Install Oracle Grid Infrastructure 27 8. Verify the Grid Infrastructure Installation 29		2.4 Virtual Disk Layout
2.7 Physical Architecture 10 Logical Architecture 11 3. Overview of Deployment Steps 12 4. Configure NTP Client on all ESX Hosts 13 5. Prepare a Virtual Machine for the First RAC Node 15 5.1 Create a Virtual Machine 15 5.2 Add Two NICs 15 5.3 Add CRS and Voting Disk 16 5.4 Install the Guest Operating System 20 5.5 Install VMware Tools 21 5.6 Time Keeping with Linux Guest Operation System 22 6. Prepare Subsequent Virtual Machine/RAC Node 23 6.1 Clone the First Virtual Machine/RAC Node 23 6.2 Change the Hostname and Assign an IP Address 23 6.3 Configure CSR and Voting Disks 24 6.4 Format the Added Disks Using fdisk. 26 7. Install Oracle Grid Infrastructure 27 8. Verify the Grid Infrastructure Installation 29		2.5 Oracle RAC Database Environment
Logical Architecture 11 3. Overview of Deployment Steps 12 4. Configure NTP Client on all ESX Hosts 13 5. Prepare a Virtual Machine for the First RAC Node 15 5.1 Create a Virtual Machine 15 5.2 Add Two NICs 15 5.3 Add CRS and Voting Disk 16 5.4 Install the Guest Operating System 20 5.5 Install VMware Tools 21 5.6 Time Keeping with Linux Guest Operation System 22 6. Prepare Subsequent Virtual Machine/RAC Node 23 6.1 Clone the First Virtual Machine/RAC Node 23 6.2 Change the Hostname and Assign an IP Address 23 6.3 Configure CSR and Voting Disks 24 6.4 Format the Added Disks Using fdisk. 26 7. Install Oracle Grid Infrastructure 27 8. Verify the Grid Infrastructure Installation 29		2.6 Network Configuration
3. Overview of Deployment Steps 12 4. Configure NTP Client on all ESX Hosts 13 5. Prepare a Virtual Machine for the First RAC Node 15 5.1 Create a Virtual Machine 15 5.2 Add Two NICs 15 5.3 Add CRS and Voting Disk 16 5.4 Install the Guest Operating System 20 5.5 Install VMware Tools 21 5.6 Time Keeping with Linux Guest Operation System 22 6. Prepare Subsequent Virtual Machines/RAC Nodes 23 6.1 Clone the First Virtual Machine/RAC Node 23 6.2 Change the Hostname and Assign an IP Address 23 6.3 Configure CSR and Voting Disks 24 6.4 Format the Added Disks Using fdisk 26 7. Install Oracle Grid Infrastructure 27 8. Verify the Grid Infrastructure Installation 29		-
 4. Configure NTP Client on all ESX Hosts		Logical Architecture11
5. Prepare a Virtual Machine for the First RAC Node 15 5.1 Create a Virtual Machine 15 5.2 Add Two NICs 15 5.3 Add CRS and Voting Disk 16 5.4 Install the Guest Operating System 20 5.5 Install VMware Tools 21 5.6 Time Keeping with Linux Guest Operation System 22 6. Prepare Subsequent Virtual Machines/RAC Nodes 23 6.1 Clone the First Virtual Machine/RAC Node 23 6.2 Change the Hostname and Assign an IP Address 23 6.3 Configure CSR and Voting Disks 24 6.4 Format the Added Disks Using fdisk. 26 7. Install Oracle Grid Infrastructure 27 8. Verify the Grid Infrastructure Installation 29	3.	Overview of Deployment Steps12
5.1Create a Virtual Machine155.2Add Two NICs155.3Add CRS and Voting Disk165.4Install the Guest Operating System205.5Install VMware Tools215.6Time Keeping with Linux Guest Operation System226.Prepare Subsequent Virtual Machines/RAC Nodes236.1Clone the First Virtual Machine/RAC Node236.2Change the Hostname and Assign an IP Address236.3Configure CSR and Voting Disks246.4Format the Added Disks Using fdisk267.Install Oracle Grid Infrastructure278.Verify the Grid Infrastructure Installation29	4.	Configure NTP Client on all ESX Hosts13
5.2Add Two NICs155.3Add CRS and Voting Disk165.4Install the Guest Operating System205.5Install VMware Tools215.6Time Keeping with Linux Guest Operation System226.Prepare Subsequent Virtual Machines/RAC Nodes236.1Clone the First Virtual Machine/RAC Node236.2Change the Hostname and Assign an IP Address236.3Configure CSR and Voting Disks246.4Format the Added Disks Using fdisk267.Install Oracle Grid Infrastructure278.Verify the Grid Infrastructure Installation29	5.	Prepare a Virtual Machine for the First RAC Node
5.3Add CRS and Voting Disk165.4Install the Guest Operating System205.5Install VMware Tools215.6Time Keeping with Linux Guest Operation System226.Prepare Subsequent Virtual Machines/RAC Nodes236.1Clone the First Virtual Machine/RAC Node236.2Change the Hostname and Assign an IP Address236.3Configure CSR and Voting Disks246.4Format the Added Disks Using fdisk267.Install Oracle Grid Infrastructure278.Verify the Grid Infrastructure Installation29		5.1 Create a Virtual Machine15
5.4Install the Guest Operating System205.5Install VMware Tools215.6Time Keeping with Linux Guest Operation System226.Prepare Subsequent Virtual Machines/RAC Nodes236.1Clone the First Virtual Machine/RAC Node236.2Change the Hostname and Assign an IP Address236.3Configure CSR and Voting Disks246.4Format the Added Disks Using fdisk267.Install Oracle Grid Infrastructure278.Verify the Grid Infrastructure Installation29		5.2 Add Two NICs
5.5Install VMware Tools		5.3 Add CRS and Voting Disk16
5.6 Time Keeping with Linux Guest Operation System226. Prepare Subsequent Virtual Machines/RAC Nodes236.1 Clone the First Virtual Machine/RAC Node236.2 Change the Hostname and Assign an IP Address236.3 Configure CSR and Voting Disks246.4 Format the Added Disks Using fdisk267. Install Oracle Grid Infrastructure278. Verify the Grid Infrastructure Installation29		5.4 Install the Guest Operating System
6. Prepare Subsequent Virtual Machines/RAC Nodes 23 6.1 Clone the First Virtual Machine/RAC Node 23 6.2 Change the Hostname and Assign an IP Address 23 6.3 Configure CSR and Voting Disks 24 6.4 Format the Added Disks Using fdisk 26 7. Install Oracle Grid Infrastructure 27 8. Verify the Grid Infrastructure Installation 29		5.5 Install VMware Tools21
6.1 Clone the First Virtual Machine/RAC Node 23 6.2 Change the Hostname and Assign an IP Address 23 6.3 Configure CSR and Voting Disks 24 6.4 Format the Added Disks Using fdisk 26 7. Install Oracle Grid Infrastructure 27 8. Verify the Grid Infrastructure Installation 29		5.6 Time Keeping with Linux Guest Operation System
 6.2 Change the Hostname and Assign an IP Address	6.	Prepare Subsequent Virtual Machines/RAC Nodes23
 6.3 Configure CSR and Voting Disks		6.1 Clone the First Virtual Machine/RAC Node23
 6.4 Format the Added Disks Using fdisk		6.2 Change the Hostname and Assign an IP Address23
 Install Oracle Grid Infrastructure		6.3 Configure CSR and Voting Disks24
8. Verify the Grid Infrastructure Installation		6.4 Format the Added Disks Using fdisk26
-	7.	Install Oracle Grid Infrastructure27
9. Add DATA and REDO Disks to Virtual Machine RAC Nodes	8.	Verify the Grid Infrastructure Installation
	9.	Add DATA and REDO Disks to Virtual Machine RAC Nodes
10. Create DATA and REDO ASM Disk Groups as Grid User	10.	Create DATA and REDO ASM Disk Groups as Grid User35
11. Install and Create the Oracle Database 11gR2 RAC	11.	Install and Create the Oracle Database 11gR2 RAC
12. References	12.	References
13. Appendix A: Deployment of Oracle RAC with RDM	13.	Appendix A: Deployment of Oracle RAC with RDM

Oracle RAC on VMware vSphere Deployment Guide

13.1 Deployment Steps for Oracle RAC on vSphere with RDM	38
13.2 Virtual Disk Layout	38
13.3 Create a Virtual Machine	41
13.4 Add CRS and Voting Disk	41
13.5 Add DATA and REDO Disks to Virtual Machine RAC Nodes	44

1. Introduction

This document describes an installation example of Oracle Real Application Clusters (RAC) on the VMware vSphere [™] platform, for Oracle DBAs planning to virtualize Oracle RAC on the VMware platform. The reader is assumed to have some hands-on experience with the VMware vSphere client. A database administrator should work with a VMware and storage administrator to successfully install Oracle RAC on VMware.

Some aspects of the virtualized installation are the same as with a physical installation:

- After virtual machines are created and correctly configured, the installation of the guest OS and Oracle RAC software is the same as with a physical installation.
- Storage layout guidelines for Oracle Database on VMware, with respect to the number of LUNs and maximizing I/O performance, are the same as with a physical installation.

Because installation details are specific to the software versions used in this deployment, there might be differences from this document if using different versions. In some cases the installation steps in this document are at high level – in these situations the detailed procedures can be found in referenced Oracle and VMware installation guides / knowledge base articles.

The sizes of VMware ESX[™] virtual machines (memory, CPU and virtual CPU) used in this document are not based on any specific business scenario. These configuration parameters are different in customer deployments and depend on customer-specific sizing requirements.

The major software components used in this installation are:

- VMware ESX 4.1 Update 1 VMware ESX abstracts processor, memory, storage and networking resources into multiple virtual machines, increasing hardware utilization.
- VMware vCenter[™] Server 4.1 Update 1 Delivers comprehensive virtualization, management, resource optimization, application availability and operational automation into an integrated product suite.
- VMware vSphere Client 4.1 Delivers comprehensive virtualization, management, resource optimization, application availability and operational automation into an integrated product suite.
- Oracle Database 11g Release 2 Grid Infrastructure (GRID) Oracle RAC uses multiple Oracle instances on multiple nodes (servers) to connect to single database.
- Oracle Database 11g Release 2 The latest RDBMS Server from Oracle.
- Oracle Automatic Storage Management (ASM) ASM integrates the file system with the volume manager designed for Oracle files.
- Oracle Enterprise Linux x86_64 5.5.

For the VMware Oracle support policy, go to http://www.vmware.com/support/policies/oracle-support.html.

2. Infrastructure Environment

This section summarizes the infrastructure environment and covers hardware, software versions, virtual machines deployed, storage, and network configuration.

2.1 Hardware

Component	Quantity	Configuration
VMware ESX Hosts	4	Cisco UCS blades 2 x 6 core CPUs, 196GB RAM and 4 NICs
Storage	1	EMC CLARiiON storage system (FC-based array)
Ethernet Switches	4	Cisco 3750
FC Switches	2	Cisco MDS 9134
Host Based Adapters	8	2 per physical server

2.2 Software Environment

Component	Version	Purpose
VMware vSphere	4.1 U1	Hypervisor hosting all virtual machines
VMware vCenter	4.1 U1	Management of VMware vSphere
Oracle Enterprise Linux x86_64	5.5	Guest operating system for virtual machines running Oracle Database server
Oracle Database 11g (with Oracle RAC and Oracle Grid Infrastructure) Enterprise Edition	11.2.0.1	Oracle cluster database software for grid computing
Microsoft Windows Server	2008 R2	Operating system to host vCenter Server

2.3 VMware Virtual Machines

Virtual Machine Role	Quantity	Configuration
Oracle RAC nodes	4	8vCPU, 128GB RAM, Oracle Enterprise Linux x86_64 5.5
VMware vCenter	1	2 vCPUs, 8GB RAM, Windows Server 2008 R2

2.4 Virtual Disk Layout

Datastore Name	Virtual Disk on ESX	Guest OS Device Name	Virtual Device	Virtual SCSI Driver	Size (GB)	Purpose
VMDATASTORE	VMDK – Hard disk 1	/dev/sda	SCSI 0:0	LSI Logic	50	Oracle Enterprise Linux 5.5 OS and Oracle binaries
CRS1	VMDK – Hard disk 2	Shared disk /dev/sdb1	SCSI 1:0	Paravirtual	20	CRS and voting disk
CRS2	VMDK – Hard disk 3	Shared disk /dev/sdc1	SCSI 1:1	Paravirtual	20	CRS and voting disk
CRS3	VMDK – Hard disk 4	Shared disk /dev/sdd1	SCSI 1:2	Paravirtual	20	CRS and voting disk
VMFSDATA01	VMDK – Hard disk 5	Shared disk /dev/sde	SCSI 1:3	Paravirtual	300	RAC database DATA
VMFSDATA02	VMDK – Hard disk 6	Shared disk /dev/sdf1	SCSI 1:4	Paravirtual	300	RAC database DATA
VMFSDATA03	VMDK – Hard disk 7	Shared disk /dev/sdg1	SCSI 1:5	Paravirtual	300	RAC database DATA
VMFSDATA04	VMDK – Hard disk 8	Shared disk /dev/sdh1	SCSI 1:6	Paravirtual	300	RAC database DATA
VMFSDATA05	VMDK – Hard disk 9	Shared disk /dev/sdi1	SCSI 1:8	Paravirtual	300	RAC database DATA
VMFSDATA06	VMDK – Hard disk 10	Shared disk /dev/sdj1	SCSI 1:9	Paravirtual	300	RAC database DATA
VMFSDATA07	VMDK – Hard disk 11	Shared disk /dev/sdk1	SCSI 1:10	Paravirtual	300	RAC database DATA
VMFSDATA08	VMDK – Hard disk 12	Shared disk /dev/sdl1	SCSI 1:11	Paravirtual	300	RAC database DATA
VMFSDATA09	VMDK – Hard disk 13	Shared disk /dev/sdm1	SCSI 1:12	Paravirtual	300	RAC database DATA
VMFSDATA10	VMDK – Hard disk 14	Shared disk /dev/sdn1	SCSI 1:13	Paravirtual	300	RAC database DATA

Datastore Name	Virtual Disk on ESX	Guest OS Device Name	Virtual Device	Virtual SCSI Driver	Size (GB)	Purpose
VMFSREDO01	VMDK – Hard disk 15	Shared disk /dev/sdo1	SCSI 2:0	Paravirtual	64	RAC database REDO
VMFSREDO02	VMDK – Hard disk 16	Shared disk /dev/sdp1	SCSI 2:1	Paravirtual	64	RAC database REDO
VMFSRED003	VMDK – Hard disk 17	Shared disk /dev/sdq1	SCSI 2:2	Paravirtual	64	RAC database REDO
VMFSREDO04	VMDK – Hard disk 18	Shared disk /dev/sdr1	SCSI 2:3	Paravirtual	64	RAC database REDO

2.5 Oracle RAC Database Environment

Node Name	ASM Instance	RAC Instance	Database	ASM Storage
VMORARAC1.vmware.com	+ASM1	VMORARAC1	VMORARAC	ASM file system
VMORARAC2.vmware.com	+ASM2	VMORARAC2	VMORARAC	ASM file system
VMORARAC3.vmware.com	+ASM3	VMORARAC3	VMORARAC	ASM file system
VMORARAC4.vmware.com	+ASM4	VMORARAC4	VMORARAC	ASM file system

2.6 Network Configuration

All four nodes in the cluster must be able to communicate with each other and with external clients using TCP/IP. Communication between clients and the nodes in the cluster is across the public network. All nodes need a network adapter configured for the public network.

To enable high availability and failover, a virtual IP (VIP) address is also required for each node. A VIP address can be moved between nodes in case of a failure. CRS manages the VIP addresses. To support a virtual IP address, both nodes require an unused IP address that is compatible with the public network's subnet and subnet mask.

For communications between instances running on the four nodes, a private network is required. This private network connects only the nodes in the cluster and cannot be accessed from outside the cluster. All nodes need a separate network adapter configured for this private network.

This deployment uses the following network configuration:

- Four physical network interface cards (NIC) vmnic1 and vmnic5 for Oracle Public and Oracle Private, vmnic0 for ESX Console and vmnic2 for vMotion.
- Two virtual switches Oracle Public (vSwitch1) and Oracle Private (vSwitch2).
- Three static IP addresses per server example for node 1 (VMORARAC1):
 - One public static IP address (eth0): 10.1.1.30
 - One private static IP address (eth1): 192.168.2.30
 - One virtual static IP address(VIP): 10.1.1.40

The physical NIC vmnic0 (Gigabit recommended) is connected to the public network which is then connected to public virtual switch vSwitch1. The Service Console is also connected to vSwitch0, and vMotion is connected to vSwitch3. The physical NIC vmnic1 is connected to the private network which is connected to the private virtual switch vSwitch2. The RAC network is also connected to vSwitch1. To create virtual switches vSwitch1 and vSwitch2, refer to the networking section of the *ESX Configuration Guide*

http://www.vmware.com/pdf/vsphere4/r41/vsp_41_esx_server_config.pdf.

Each server in the cluster requires three IP addresses. One IP address is for the public network connected to the public network virtual switch (Oracle Public), and a second IP address is for the private cluster interconnects connected to the private network virtual switch (Oracle Private). The third IP address, which is a virtual IP address, is configured by Oracle when Oracle Grid Infrastructure is installed.

Figure 1. Network Configuration

Hardware	View: Virtual Switch vNetwork D	istributed Switch	
Processors Memory Storage • Networking Storage Adapters	Virtual Switch: vSwitch0 Virtual Machine Port Girsup	Physical Adapters	
Network Adapters Advanced Settings Power Management	Service Console Port	2-+-	
Software			
Licensed Features Time Configuration DNS and Routing Authentication Services Power Management	Virtual Switch: vSwitch1 Virtual Machine Port Group Oracle Public I virtual machine(s) VMORARAC2	Physical Adapters	For Oracle RAC – Public
Virtual Machine Startup/Shutdown Virtual Machine Swapfile Location Security Profile System Resource Allocation Advanced Settings	 1 virtual machine(s) 	Remove Properties Physical Adapters Physical Adapters Physica	and Private
	Virtual Switch: vSwitch3	Remove Properties	
	VMkernel Port VMkernel vmkD : 192.168.3.3	Physical Adapters	

© 2011 VMware, Inc. All rights reserved.

4 Gig Fibre Channel

2.7 Physical Architecture

The following architecture diagram depicts the physical architecture of the Oracle RAC deployment environment on VMware vSphere 4.1.



Figure 2. Physical Architecture of Oracle RAC on vSphere

Logical Architecture

The following diagram describes the logical architecture of a two-node RAC on VMware vSphere 4.1. The actual deployment uses four nodes.





3. Overview of Deployment Steps

The following process diagram illustrates the deployment steps for deploying a four-node Oracle RAC on VMware vSphere 4.1 with VMFS. For deploying Oracle RAC with RDM refer Appendix A: Deployment of Oracle RAC with RDM.



Figure 4. Deployment Steps for Four-Node Oracle RAC on vSphere with VMFS

4. Configure NTP Client on all ESX Hosts

The correct system time is required with Oracle Database. VMware Tools has an option to allow virtual machines to synchronize the time with the ESX host they are running on. All ESX hosts in a given resource cluster should synchronize their system clocks.

ESX hosts include NTP software and start the ntpd service by default. ESX hosts are not configured to actually make use of NTP upon installation, nor is there anything in the standard installation process which gives the administrator the option to set this. In the four-node example, synchronizing the time is done for all four ESX hosts.

To configure the NTP client settings

- 1. Click Properties to display the NTP Daemon (ntpd) Options dialog box.
- 2. Click NTP Settings.
- 3. Click Add to add NTP servers.

Figure 5. NTP Daemon (ntpd) Options - NTP Settings

🛃 NTP Daemon (ntpd) Opti	ons	×
General NTP Settings	NTP Servers	
	Restart NTP service to apply changes	
	OK Cancel Help	

- 4. For the **Startup Policy**, select the **Start and stop with host** option.
- 5. Click OK.

Figure 6. NTP Daemon (ntpd) Options – General

🛃 NTP Daemon (ntpd) Opl	tions	×
General NTP Settings	Status Running Startup Policy Start automatically Start and stop with host Start and stop manually Start Start	
	OK Cancel <u>H</u> elp	

6. After the configuration is complete, the configuration screen looks similar to the following illustration.

Figure 7. VMware ESX Configuration Screen

Hardware	Time Configuration		
Processors	General		
Memory	Date & Time	14:13 4/26/2011	
Storage	NTP Client	Running	
Networking	NTP Servers	171.68.10.80, 10.81.254.131	
Storage Adapters		·	
Network Adapters			
Advanced Settings			
Power Management			
Software			
Licensed Features			
 Time Configuration 			
DNS and Routing			
Authentication Services			
Power Management			
Virtual Machine Startup/Shutdown			
Virtual Machine Swapfile Location			
Security Profile			
System Resource Allocation			
Advanced Settings			

5. Prepare a Virtual Machine for the First RAC Node

This section describes the following steps:

- Creation of the first virtual machine, which is the first RAC node, using the vSphere client. This is
 created on VMFS and corresponds to the root drive. Two NICs are assigned for the public and private
 networks. Three datastores, CRS1, CRS2, and CRS3, are created from the storage LUNs and three
 VMDKs are created and assigned to the virtual machine for CRS and voting. Only one VMDK is
 required but three are used for redundancy.
- Installation of the Linux operating system in the virtual machine followed by installation of VMware Tools.
- Synchronization of the time within the guest OS with the ESX host.

5.1 Create a Virtual Machine

Four ESX hosts have been created and are visible in vCenter.

To create a new virtual machine

- 1. Log in to vCenter using the vSphere client.
- 2. Select a host and click Create a new virtual machine on the Getting Started tab.
- 3. In the Create New Virtual Machine wizard, select Typical for the Configuration, and click Next.
- 4. On the Name and Location page, enter VMORARAC1 for the Name, and click Next.
- 5. On the **Datastore** page, select **VMDATASTORE**, and click **Next**.
- 6. On the Guest Operating System page, select Linux from the Guest Operating System list. For the Version, select Oracle Linux 4/5 (64-bit) from the drop-down menu. Click Next.
- 7. On the Create a Disk page, set the Virtual Disk Size to 50GB, and click Next.
- 8. On the **Ready to Complete** page, select the **Edit the virtual machine settings before completion** check box. Click **Continue**.
- 9. On the Virtual Machine Properties page for the VMORARAC1 virtual machine, select 8 CPUs and 128GB Memory.
- 10. Click Finish.

5.2 Add Two NICs

In this section, two NICs are added. One NIC is for the public network, and the other is for the private network. The procedure for each is similar, differing only in the selection of **RAC Public** or **Private** for the network label.

To add a NIC to the virtual machine for the public network

- 1. Select a virtual machine
- 2. Click Edit settings to display the Virtual Machine Properties pane
- 3. Click Add.
- 4. Select Ethernet Adaptor and click Next to display the Add Hardware wizard.
- 5. On the **Network connection** page, select **VMXNET 3** from the **Adapter Type** drop-down menu.
- 6. In the **Network Connection** section of the **Network connection** page, select **Named network with specified label**.

© 2011 VMware, Inc. All rights reserved.

- 7. In the Named network with specified label drop-down menu, select RAC Public.
- 8. In the **Device Status** section of the **Network connection** page, select the **Connect at power on** check box.
- 9. On the Ready to Complete page, click Finish, and then click OK.

To add a NIC to the virtual machine for the private network

- 1. Repeat steps 1 through 7 from the preceding procedure
- 2. In the Named network with specified label drop-down menu, select Private.
- 3. Continue with steps 9 and 10 from the preceding procedure

5.3 Add CRS and Voting Disk

Three 20GB disks are created and VMDKs are created and added to the virtual machine for RAC CRS and voting. Although only one is required, three are used for redundancy. The datastores are created from the assigned LUNs which are attached to a SCSI controller configured as VMware Paravirtual. The SCSI BUS sharing policy of the SCSI controller is set to none.

The procedures in this section describe the steps needed to create disks for one virtual machine. Repeat all the steps in this section for each of the four virtual machines named VMORARAC1, VMORARAC2, VMORARAC3, and VMORARAC4.

To create one 20GB datastore for a virtual machine

- 1. In the vSphere client, select a virtual machine.
- 2. Right-click on the name of the virtual machine and select **Edit Settings** to display the **Virtual Machine Properties** pane.
- 3. Click Add to display the Add Hardware wizard.
- 4. In the Add Hardware wizard select Hard Disk for the Device Type, and click Next.
- In the Disk section of the Select a Disk page, select Create a new virtual disk. Set the disk size to 20GB, select the Support clustering features such as Fault Tolerance check box, and select CRS1 to specify a datastore. Click Next.
- 6. On the **Compatibility Mode** page, click **Next**.
- 7. On the Advanced Options page, in the Virtual Device Node section, select SCSI (1:0). In the Mode section, select Independent. Click Next
- 8. On the Ready to Complete page, click Finish.
- 9. Click OK.

To create a second 20GB datastore for the virtual machine

- 1. Select the virtual machine that was selected in the preceding step 1.
- 2. Repeat steps 2 through 6 in the preceding procedure to create one 20GB datastore.
- 3. On the Advanced Options page, in the Virtual Device Node section, select SCSI (1:1). In the Mode section, select Independent. Click Next.
- 4. Repeat steps 8 and 9 of the preceding procedure to create one 20GB datastore.

To create a third 20GB datastore for the virtual machine

- 1. Select the virtual machine that was selected in the preceding step 1.
- 2. Repeat steps 2 through 6 in the preceding procedure to create one 20GB datastore.
- 3. On the Advanced Options page, in the Virtual Device Node section, select SCSI (1:2). In the Mode section, select Independent. Click Next.
- 4. Repeat steps 8 and 9 of the preceding procedure to create one 20GB datastore.

To set the SCSI controller type to paravirtual

- 1. Select the virtual machine that was selected in the preceding step 1.
- 2. Right-click on the name of the virtual machine and select **Edit Settings** to display the **Virtual Machine Properties** pane.
- 3. In the device list, select SCSI controller 1.
- 4. In the SCSI Bus Sharing section, select None, keep the default selection.
- 5. In the SCSI Controller Type section, click Change Type.
- 6. Select VMware Paravirtual.
- 7. Click OK, and click OK again.

Add Configuration parameters for each Oracle RAC virtual machine as described in *Disabling simultaneous write protection provided by VMFS using the multi-writer flag* <u>http://kb.vmware.com/kb/1034165</u>.

To add configuration parameters to the virtual machines

- 1. In the vSphere client, select a virtual machine.
- 2. Right-click on the name of the virtual machine and select **Edit Settings** to display the **Virtual Machine Properties** pane.
- 3. Click the **Options** tab, click **Advanced**, and click **General**.
- 4. Click Configuration Parameters.
- 5. On the **Configuration Parameters** page, add rows and entries for the shared disks in the virtual machine's configuration parameters as shown in the following screenshot.
- 6. Repeat steps 1 through 5 for each of the remaining virtual machines.

Figure 8.	Virtual	Machine	Configura	ation	Parameters
			Jungano		

🛃 VMORA	RAC2 - Virtual N	1achine Properties
Hardware	Options Resour	rces Virtual Machine Version: 7
Settings		Summary Settings
Conoral		
VApp C	Configuration	Parameters X
VMware	Modify or add con	figuration parameters as needed for experimental features or as instructed by technical support.
Power I	Entries cannot be	removed.
Advanc	Name 🗠	Value
Gene	pciBridge5.fu	8
CPUI	pciBridge6.pr	true
Memo	pciBridge6.vir	pcieRootPort
Boot	pciBridge6.fu	8
Fibre	pciBridge7.pr	true
CPU/	pciBridge7.vir	pcieRootPort
Swap	pciBridge7.fu	8
	vmware.tools	
	sched.swap.d	/vmfs/volumes/4d64fb74-86c5743c-77ca-0025b5aabb1f/VMORARAC2/VMORARAC2-6b6169a
	scsi1:0.sharing	multi-writer
	scsi1:1.sharing	multi-writer
	scsi1:2.sharing	multi-writer
	•	
		Add Row
		OK Cancel Help
		li
Help		OK Cancel

You can view the virtual machine properties for the VMORARAC2 virtual machine in vCenter as in the following screenshot.

ardware Options Resources	
Show All Devices	Add Remove
lardware	Summary
Memory	131072 MB
🔲 CPUs	8
📃 Video card	Video card
VMCI device	Restricted
SCSI controller 0	LSI Logic Parallel
 VMCI device SCSI controller 0 SCSI controller 1 SCSI controller 2 	Paravirtual
SCSI controller 2	Paravirtual
Hard disk 1	Virtual Disk
🚍 🛛 Hard disk 2	Virtual Disk
😅 🛛 Hard disk 3	Virtual Disk
😅 🛛 Hard disk 4	Virtual Disk
😅 🛛 Hard disk 5	Virtual Disk
😅 🛛 Hard disk 6	Virtual Disk
😅 🛛 Hard disk 7	Virtual Disk
😅 🛛 Hard disk 8	Virtual Disk
😅 🛛 Hard disk 9	Virtual Disk
😅 🛛 Hard disk 10	Virtual Disk
😅 🛛 Hard disk 11	Virtual Disk
Hard disk 12	Virtual Disk
😅 Hard disk 13	Virtual Disk
Hard disk 14	Virtual Disk
Hard disk 15	Virtual Disk
Hard disk 16	Virtual Disk
😅 Hard disk 17	Virtual Disk
Hard disk 18	Virtual Disk
CD/DVD Drive 1	[]
😨 Network adapter 1	Oracle Public
Network adapter 2	Oracle Private

5.4 Install the Guest Operating System

The Oracle Enterprise Linux 5.5 x64 operating system is installed from an ISO image that has been loaded into a VMFS datastore.

To install Linux as the guest operating system in a virtual machine

- 1. In the vSphere client, select a virtual machine.
- 2. Click on Edit settings
- 3. In the Hardware tab of the Virtual Machine Properties pane, select CD/DVD Drive 1.
- 4. In the **Device Status** section of this pane, select the **Connect at power on** check box.
- 5. In the **Device Type** section of this pane, select **Datastore ISO File** and enter the path to your Linux ISO image file.
- 6. In the Virtual Device Node section of this pane, select IDE (1:0) CD/DVD Drive 1 from the drop-down menu.
- 7. Click **OK**.
- 8. Power on the virtual machine.
- 9. Install Linux with the following settings.

Custom partitioning scheme:

```
/dev/sda1 ext3 15GB mounted on /
/dev/sda2 ext3 25GB mounted on /u01
/dev/sda3 swap 10GB
```

Installed packages – use the default package selection, plus the following:

- oracle-validated-1.0.0-22.el5.x86_64
- oracleasm-2.6.18-194.el5-2.0.5-1.el5.x86_64
- oracleasm-support-2.1.3-1.el5.x86_64
- systat-7.0.2-3.el5.x86_64
- 10. Download and install the ASM library from the Oracle Web site: http://www.oracle.com/technetwork/topics/linux/asmlib/index-101839.html

11. View the installed packages with this command:

run command "rpm -q <package name>

- 12. Confirm that the following packages have been installed:
 - binutils-2.17.50.0.6
 - compat-libstdc++-33-3.2.3
 - elfutils-libelf-0.125
 - elfutils-libelf-devel-0.125
 - elfutils-libelf-devel-static-0.125
 - gcc-4.1.2
 - gcc-c++-4.1.2
 - glibc-2.5-24
 - glibc-common-2.5
 - glibc-devel-2.5
 - glibc-headers-2.5

- ksh-20060214
- libaio-0.3.106
- libaio-devel-0.3.106
- libgcc-4.1.2
- libstdc++-4.1.2
- libstdc++-devel 4.1.2
- make-3.81
- sysstat-7.0.2
- unixODBC-2.2.11
- unixODBC-devel-2.2.11

5.5 Install VMware Tools

VMware Tools is a suite of utilities that enhance the performance of the virtual machine's guest operating system and improve management of the virtual machine. VMware Tools must be installed inside the guest OS. The installation steps are described in *Installing VMware Tools in a Linux virtual machine using Red Hat Package Manager (RPM)*

http://kb.vmware.com/selfservice/microsites/search.do?language=en_US&cmd=displayKC&externalId=10 18392.

To install VMware Tools

- 1. Confirm that the Linux virtual machine is powered on.
- 2. In the vSphere client, right click on the virtual machine and select Guest > Install VMware Tools.
- 3. In the Linux guest OS, create a mount point and run the following command:

mkdir /mnt/cdrom

4. Mount the CD-ROM with the following command:

```
mount /dev/cdrom /mnt/cdrom
```

5. Install VMware Tools using RPM, with the following command

```
rpm -ivh /mnt/cdrom/VMwareTools-8.3.2-257589.rpm
```

"8.3.2-257589" is the version of VMware Tools used here.

6. Configure VMware Tools, by running the following command

/usr/bin/vmware-config-tools.pl

7. Unmount the CD-ROM with the following command

umount /mnt/cdrom

8. Click VM in the virtual machine menu, and click Guest > End VMware Tools Install.

© 2011 VMware, Inc. All rights reserved.

5.6 Time Keeping with Linux Guest Operation System

Next, follow <u>VMware KB: 1006427</u> recommendations to configure NTP and when using NTP in the guest, disable VMware Tools *periodic* time synchronization.

To disable VMware Tools periodic time sync, perform one of these options:

1. Set tools.syncTime = "False" in the configuration file (.vmx file) of the virtual machine.

OR

2. Deselect **Time synchronization between the virtual machine and the host operating system** in the VMware Tools toolbox GUI of the guest operating system.

OR

3. Run the vmware-guestd --cmd "vmx.set_option synctime 1 0" command in the guest operating system.

For ESX 4.x, Use these parameters for Linux:

- 1. To display the current status of the service vmware-toolbox-cmd timesync status
- 2. Disables periodic time syncronization

vmware-toolbox-cmd timesync disable

6. Prepare Subsequent Virtual Machines/RAC Nodes

Now that the first RAC node virtual machine (VMORARAC1) has been created, this virtual machine can be cloned to create the remaining three cluster node virtual machines. The high level procedure is:

- In vCenter clone VMORARAC1.
- On the newly created virtual machine remove the three RDM virtual disks that came over from the source virtual machine.
- Attach the same three VMFS disks (VMDKs) for CSR and voting as used by the first virtual machine, VMORARAC1. These three disks were configured to be shared by multiple virtual machines using the procedures outlined in *Disabling simultaneous write protection provided by MVFS using the multiwriter flag* http://kb.ymware.com/kb/1034165.
- Change the hostname and IP address in the guest OS.

6.1 Clone the First Virtual Machine/RAC Node

To clone the first virtual machine for the second, third, and fourth nodes

- 1. Confirm that the first virtual machine VMORARAC1 is offline.
- 2. In the vSphere client, select the virtual machine, VMORARAC1.
- 3. Right-click on the name of the virtual machine and select Clone.
- 4. In the Clone Virtual Machine wizard on the Name and Location page, enter VMORARAC2 for the Name. Click Next.
- 5. On the **Host / Cluster** page, select a host or cluster. Click **Next**.
- 6. On the **Specific Host** page, select a unique ESX host (that is, one not running a RAC node virtual machine). Click **Next**.
- 7. On the Datastore page, select a VMFS datastore. Click Next.
- 8. On the **Disk Format** page, select **Same format as source**. Click **Next**.
- 9. On the Guest Customization page, select Do not customize.
- 10. On the Ready to Complete page, click Finish.
- 11. Repeat steps 1 through 10 for nodes 3 and 4 using VMORARAC3 and VMORARAC4 in step 4.

6.2 Change the Hostname and Assign an IP Address

To assign unique names and IP addresses to each RAC Node virtual machine

- 1. Using the console, log in as root to the VMORARAC2 cloned virtual machine.
- 2. Go to **System > Administration > Network**.
- 3. On the **Devices** tab, change the IP address for eth0 and eth1, with the required subnet masks:
 - a. For eth0, change the IP address from 10.1.1.30 to **10.1.1.31**.
 - b. For eth1, change the IP address from 192.168.2.30 to 192.168.2.31.
- 4. On **DNS** tab, change the hostname from VMORARAC1 to **VMORARAC2**.
- 5. Repeat steps 1 through 4 for the remaining two virtual machines (VMORARAC3 and VMORARAC4), using appropriate IP addresses and subnet masks in steps 3a and 3b, and the corresponding hostname in step 4.

© 2011 VMware, Inc. All rights reserved.

6.3 Configure CSR and Voting Disks

The new virtual machine has been cloned, but the links to Hard disks 2, 3 and 4 are incorrect. These are removed so that one disk (VMFS) remains, corresponding to the root drive. The CSR and voting disks are then added. Finally, the SCSI controller type is changed to paravirtual.

The procedures in this section describe the steps needed for one virtual machine. Repeat all the steps in this section for each of the four virtual machines named VMORARAC1, VMORARAC2, VMORARAC3, and VMORARAC4.

To remove incorrect links from the clone

- 1. In the vSphere client, select a virtual machine.
- 2. Right-click on the name of the virtual machine and select **Edit Settings** to display the **Virtual Machine Properties** pane.
- 3. Select Hard disk 2 and click **Remove**. In the **Removal Options** section, select **Remove from virtual machine** and click OK.
- 4. Select Hard disk 3 and click **Remove**. In the **Removal Options** section, select **Remove from virtual machine** and click OK.
- 5. Select Hard disk 4 and click **Remove**. In the **Removal Options** section, select **Remove from virtual machine** and click OK.

To add the first CSR and voting disk for a virtual machine

- 1. In the vSphere client, select a virtual machine.
- 2. Right-click on the name of a virtual machine and select **Edit Settings** to display the **Virtual Machine Properties** pane.
- 3. Click Add to display the Add Hardware wizard.
- 4. In the Add Hardware wizard select Hard Disk for the Device Type, and click Next.
- 5. In the Disk section of the Select a Disk page, select Use an existing virtual disk and click Next.
- 6. On the **Select Existing Disk** page, enter the path to the first VMDK of the virtual machine (selected in step 1) used for the CSR and voting datastores. Click **Next**.
- 7. On the Advanced Options page, in the Virtual Device Node section, select SCSI (1:0). In the Mode section, select Independent and Persistent. Click Next.
- 8. On the **Ready to Complete** page, click **Finish**.
- 9. Click OK.

To add the second CSR and voting disk for a virtual machine

- 1. Repeat steps 1 through 5 in the preceding procedure to add the first CSR and voting disk.
- 2. On the **Select Existing Disk** page, enter the path to the second VMDK of the virtual machine (selected in step 1) used for the CSR and voting datastores. Click **Next**.
- 3. On the Advanced Options page, in the Virtual Device Node section, select SCSI (1:1). In the Mode section, select Independent and Persistent. Click Next.
- 4. Repeat steps 8 and 9 in the preceding procedure to add the first CSR and voting disk.

To add the third CSR and voting disk for a virtual machine

- 1. Repeat steps 1 through 5 in the preceding Configure CSR and Voting Disks procedure to add the first CSR and voting disk.
- 2. On the **Select Existing Disk** page, enter the path to the third VMDK of the virtual machine (selected in step 1) used for the CSR and voting datastores. Click **Next**.
- 3. On the Advanced Options page, in the Virtual Device Node section, select SCSI (1:2). In the Mode section, select Independent and Persistent. Click Next.
- 4. Repeat steps 8 and 9 in the preceding procedure to add the first CSR and voting disk.

To set the SCSI controller type to paravirtual

- 1. In the vSphere client, select the virtual machine that was selected in the preceding step 1.
- 2. Right-click on the name of the virtual machine and select **Edit Settings** to display the **Virtual Machine Properties** pane.
- 3. In the device list, select SCSI controller 1.
- 4. In the SCSI Controller Type section, click Change Type.
- 5. Select VMware Paravirtual.
- 6. Click **OK**, and click **OK** again.

6.4 Format the Added Disks Using fdisk

On node 1, you must partition and format the virtual disks. You can use the Linux fdisk utility to accomplish this. Refer to the following illustration showing the output of the fdisk utility.

To partition and format three virtual disks

- 1. Log in as root on node1.
- 2. Enter the command:

fdisk /dev/sdb

- 3. Enter **n** to create a new partition.
- 4. Enter **p** to create a primary partition.
- 5. Enter 1 to create the first partition.
- 6. Press Enter to take the default value of 1 for the first cylinder.
- 7. Press Enter to take the default value of 20480 for the last cylinder.
- 8. Enter **w** to write the new partition table to disk and exit fdisk.
- 9. Repeat steps 2 through 8, using the following command for the second virtual disk:

fdisk /dev/sdc

10. Repeat steps 2 through 8, using the following command for the third virtual disk:

fdisk /dev/sdd

Figure 10. Commands to Run fdisk

```
root@vmorarac1 ~# fdisk /dev/sdb
Device contains neither a valid DOS partition table, nor Sun, SGI or OSF
disklabel
Building a new DOS disklabel. Changes will remain in memory only,
until you decide to write them. After that, of course, the previous
content won't be recoverable.
Warning: invalid flag 0x0000 of partition table 4 will be corrected by
w(rite)
Command (m for help): n
Command action
e extended
p primary partition (1-4)
р
Partition number (1-4): 1
First cylinder (1-20480, default 1):
Using default value 1
Last cylinder or +size or +sizeM or +sizeK (1-20480, default 20480):
Using default value 20480
Command (m for help): w
The partition table has been altered!
Calling ioctl() to re-read partition table.
Syncing disks.
```

7. Install Oracle Grid Infrastructure

The four virtual machines are cloned and ready for the installation of Oracle Grid Infrastucture.

To install Oracle Grid Infrastructure

- 1. Configure SSH for all the nodes to allow SSH to all nodes without a password.
- 2. Configure Oracle ASM and create three disks CRSVOL1, CRSVOL2, and CRSVOL3 from /dev/sdb1,/dev/sdc1, and /dev/sdd1 respectively.
- From VM1 (VMORARAC1) 64-bit (x86_64) Installations download unzip the following software packages (File 1 and File 2) from <u>http://www.oracle.com/technology/software/products/database/oracle11g/112010_linx86 64soft.html</u>.
 - Oracle Database 11g Release 2 Grid Infrastructure (11.2.0.1.0) for Linux x86_64
 - Oracle Database 11g Release 2 (11.2.0.1.0) for Linux x86_64
- 4. Launch the Oracle Grid Infrastructure installation wizard.
- 5. On the Installation Option page, in the Select any of the following installation options, select Install and Configure Infrastructure for a Cluster. Click Next.
- 6. On the Installation Type page, select Advanced Installation and click Next.
- 7. On the Product Languages page, select English and click Next.
- 8. On the Grid Plug and Play page, enter vmorarac for the Cluster Name, vmorarac-scan.vmware.com for the SCAN Name and 1521 for the SCAN Port. Click Next.
- 9. On the **Cluster Node Information** page, click **Add** to enter a **Hostname** and **Virtual IP Name**. Repeat the process for each of the four hosts, as follows:

Hostname	Virtual IP Name
vmorarac1.vmware.com	vmorarac1-vip.vmware.com
vmorarac2.vmware.com	vmorarac2-vip.vmware.com
vmorarac3.vmware.com	vmorarac3-vip.vmware.com
vmorarac4.vmware.com	vmorarac4-vip.vmware.com

10. Click Next.

11. On the **Network Interface Usage** page, enter the following information for the **Interface Name**, **Subnet** and **Interface Type**:

Interface Name	Subnet	Interface Type
eth0	10.1.1.0	Public
eth1	192.168.2.0	Private

12. Click Next.

- 13. On the Storage Option page, select Automatic Storage Management (ASM), and click Next.
- 14. On the Create ASM Disk Group page, enter CRS for the Disk Group Name, select Normal for Redundancy.
- 15. In the Add Disks section of the Create ASM Disk Group page, select Candidate Disks. Make the following entries:

Disk Path	Size (in MB)	Status
ORCL:CRSVOL1	20479	Candidate
ORCL:CRSVOL2	20479	Candidate
ORCL:CRSVOL3	20479	Candidate

- 16. Select the check box to the left of each of these entries, and click Next.
- 17. On the ASM Password page, select Use same passwords for these accounts and enter the password "oracle1" in the Specify Password and Confirm Password fields. Click Next.
- 18. On the Failure Isolation page, select Do not use Intelligent Platform Management Interface (IPMI). Click Next.
- 19. On the **Operating System Groups** page, make the following entries:

Field	Selection
ASM Database Administrator (OSDBA) Group	asmdba
ASM Instance Administration Operator (OSOPER) Group	asmoper
ASM Instance Administrator (OSASM) Group	asmadmin

- 20. Click Next.
- 21. On the Installation Location page, enter /u01/app/grid for the Oracle Base, and /u01/app/11.2.0/grid for the Software Location. Click Next
- 22. On the Create Inventory page, enter /u01/app/orainventory for the Inventory Directory. Click Next.
- 23. Wait while the setup application conducts the prerequisite checks and installs Grid on each node. After setup is complete, execute the following configuration scripts on the four nodes VMORARAC1, VMORARAC2, VMORARAC3, and VMORARAC4. These scripts must be executed in a terminal window as root.

```
/u01/app/orainventory/orinstRoot.sh
```

/u01/app/11.2.0/grid/root.sh

24. Click OK, and click Finish.

8. Verify the Grid Infrastructure Installation

The following figures show how to run various RAC commands in the guest OS to check the status of the cluster.

Figure 5. Check the CRS Status on the First Node as Grid User



Figure 6. Check for Cluster Nodes



Figure 7. Check for Cluster Registry (OCR)

🚰 grid@ymorarac1:~		
+ASM1 /home/grid -> ocrcheck		
Status of Oracle Cluster Registry		
Version	: 3	
Total space (kbytes)		
Used space (kbytes) Available space (kbytes)		
ID	: 1585277307	
Device/File Name	: +CR5	
	Device/File integrity check succeeded	
	Device/File not configured	
Cluster registry integri	ty check succeeded	
Logical corruption chec}	bypassed due to non-privileged user	
+ASM1 /home/grid ->		

Figure 8. Check Voting Disk

🛃 g	rid@vmorara	ac1:~		
$+\lambda$	SM1 /home	/grid -> crsctl query cs	s votedisk	▲
##	STATE	File Universal Id	File Name Disk group	
1.	ONLINE	91667ba2625c4fefbf7e2c8	938b8ebf8 (ORCL:CRSVOL1) [CRS]	
2.	ONLINE	29277d62fa324f5dbfad8b9	87c6b7332 (ORCL:CRSVOL2) [CRS]	
з.	ONLINE	490468754f174f0fbff297c	d027925e8 (ORCL:CRSVOL3) [CRS]	
Loc	ated 3 vo	ting disk(s).		
+A	SM1 / home	/grid ->		
				•

9. Add DATA and REDO Disks to Virtual Machine RAC Nodes

In this section, the database disks for data and redo logs are added to the virtual machine RAC nodes in the following way:

- Data and redo datastores are created with the assigned LUNs, and corresponding VMDKs are added to the virtual machine VMORARAC1. The SCSI controller type is set to VMware Paravirtual.
- The same Data and Redo VMDKs are added to the remaining three nodes (VMORARAC2, VMORARAC3, and VMORARAC4) by selecting the VMDKs that were created for VMORARAC1. Again, the SCSI controller type is set to VMware Paravirtual.
- The added disks are formatted using the Linux fdisk utility.
- Configuration parameters are added for each virtual machine.

The procedures in this section describe the steps needed for one virtual machine. Repeat all the steps in this section for each of the four virtual machines named VMORARAC1, VMORARAC2, VMORARAC3, and VMORARAC4.

To add DATA or REDO disks to the first virtual machine

- 1. In the vSphere client, select the virtual machine.
- 2. Right-click on the name of the virtual machine and select **Edit Settings** to display the **Virtual Machine Properties** pane.
- 3. Click Add to display the Add Hardware wizard.
- 4. In the Add Hardware wizard select Hard Disk for the Device Type, and click Next.
- In the Disk section of the Select a Disk page, select Create a new virtual disk. Set the disk size to 300GB for DATA or 64GB for REDO, and select the Support clustering features such as Fault Tolerance check box. Select VMFSDATA01 for DATA, or VMFSREDO01 for REDO to specify a datastore. Click Next.
- 6. On the **Compatibility Mode** page, click **Next**.
- 7. On the Advanced Options page, in the Virtual Device Node section, select SCSI (1:3) for DATA, or SCSI (2:0) for REDO. Set the Mode to Independent. Click Next
- 8. On the **Ready to Complete** page, click **Finish**.
- 9. Click OK.
- 10. Repeat steps 1 through 9 for all the DATA and REDO datastores. Change step 7 to use SCSI (1:4) for the next DATA datastore, or SCSI (2:1) for the next REDO datastore. For additional DATA or REDO datastores, repeat steps 1 through 9 and continue the numbering sequence in step 7. For example, the third DATA datastore uses the numbering SCSI (1:5), and the third REDO datastore uses the numbering SCSI (2:2).

To set the SCSI controller type to paravirtual

- 1. Select the virtual machine that was selected in the preceding step 1.
- 2. Right-click on the name of the virtual machine and select **Edit Settings** to display the **Virtual Machine Properties** pane.
- 3. In the device list, select SCSI controller 1.
- 4. In the SCSI Bus Sharing section, select None, keep the default selection.
- 5. In the SCSI Controller Type section, click Change Type.
- 6. Select VMware Paravirtual.
- 7. Click OK, and click OK again.

To format disks using the Linux fdisk utility

- 1. Follow the steps in Section 6.4 to format one disk.
- 2. Repeat, using fdisk to format each disk.

To add configuration parameters for each Oracle RAC virtual machine

Add Configuration parameters for each Oracle RAC virtual machine as per *Disabling simultaneous write* protection provided by VMFS using the multi-writer flag http://kb.vmware.com/selfservice/microsites/search.do?language=en_US&cmd=displayKC&externalId=10 34165.

To add configuration parameters to the virtual machines

- 1. In the vSphere client, select a virtual machine.
- 2. Right-click on the name of the virtual machine and select **Edit Settings** to display the **Virtual Machine Properties** pane.
- 3. Click the **Options** tab, click **Advanced**, and click **General**.
- 4. Click Configuration Parameters.
- 5. On the **Configuration Parameters** page, add rows and entries for the shared disks in the virtual machine's configuration parameters as shown in the following screenshot.
- 6. Repeat steps 1 through 5 for each of the remaining virtual machines.

	AC1 - Virtual Machine	Properties	
rdware	Options Resources		Virtual Machine Version:
ttings		Summary	Settings
neral Op	tions	VMORARAC1	Disable acceleration
pp Optio	ns	Disabled	
lware To	ols	Shut Down	Enable logging
wer Ma		Suspend	
Ivance 🕻	Configuration Para	neters	×
Genera			r experimental features or as instructed by technical support.
CPUID	Entries cannot be remov	ed.	
nemor	Name	Value	
Boot O	scsi1:2.redo		
Fibre C	scsi1:3.sharing	multi-writer	
PU/MI	scsi1:4.sharing	multi-writer	
ōwapfil	scsi1:5.sharing	multi-writer	
	scsi1:6.sharing	multi-writer	
	scsi1:8.sharing	multi-writer	
	scsi1:9.sharing	multi-writer	
	scsi1:10.sharing	multi-writer	
	scsi1:11.sharing	multi-writer	
	scsi1:12.sharing	multi-writer	
	scsi1:13.sharing	multi-writer	
	scsi2:0.sharing	multi-writer	
	scsi2:1.sharing	multi-writer	
	scsi2:2.sharing	multi-writer	
	scsi2:3.sharing	multi-writer	
	 •		
			Add Row
			OK Cancel Help
_			
	1		
Help			OK Cancel

Figure 9. Virtual Machine Configuration Parameters

The devices for the virtual machine should look like the following screenshot.

Figure 10. Virtual Machine Properties

lardware Options Resources		Virtual Machine Version
Show All Devices	Add Remove	Memory Configuration
		255 GB 📢 Memory Size: 128 🐳 GB 💌
Hardware	Summary	
🌃 Memory	131072 MB	128 GB Maximum recommended for this quest OS: 255 GB.
🔲 CPUs	8	
📃 Video card	Video card	64 GB Maximum recommended for best
😅 🛛 VMCI device	Restricted	Default recommended for this
🎯 SCSI controller 0	LSI Logic Parallel	32 GB Default recommended for this guest OS: 384 MB.
SCSI controller 1	Paravirtual	16 GB Minimum recommended for this
📀 SCSI controller 2	Paravirtual	■ 10 GB ■ ■ guest OS: 256 MB.
😅 🛛 Hard disk 1	Virtual Disk	8 GB -
😅 🛛 Hard disk 2	Virtual Disk	0.00
😅 🛛 Hard disk 3	Virtual Disk	4 GB
😅 🛛 Hard disk 4	Virtual Disk	
😅 🛛 Hard disk 5	Virtual Disk	2 GB <mark>-</mark>
😅 🛛 Hard disk 6	Virtual Disk	
😅 🛛 Hard disk 7	Virtual Disk	1 GB -
😅 🛛 Hard disk 8	Virtual Disk	
😅 🛛 Hard disk 9	Virtual Disk	512 MB
😅 🛛 Hard disk 10	Virtual Disk	
😅 🛛 Hard disk 11	Virtual Disk	256 MB
😅 🛛 Hard disk 12	Virtual Disk	
🚍 🛛 Hard disk 13	Virtual Disk	128 MB
😅 🛛 Hard disk 14	Virtual Disk	
😅 🛛 Hard disk 15	Virtual Disk	64 MB
😅 🛛 Hard disk 16	Virtual Disk	
😅 🛛 Hard disk 17	Virtual Disk	32 MB -
🚍 🛛 Hard disk 18	Virtual Disk	10.000
CD/DVD Drive 1	[]	16 MB
📟 Network adapter 1	Oracle Public	в мв
🔛 Network adapter 2	Oracle Private	
		4 MB

10. Create DATA and REDO ASM Disk Groups as Grid User

To prepare for the installation of Oracle Database binary and database

- 1. Using Oracle ASM, create disks DATAVOL1 through DATAVOL10 using /dev/sde1 through /dev/sde1, and disks REDOVOL1 through REDOVOL4 using /dev/sdo1 through /dev/sde1.
- Using ASM Configuration Assistant logged in as Grid user at node1 (VMORARAC), create two disk groups RACDATA (selecting all ten disks DATAVOL1 through DATAVOL10) and RACREDO (selecting all four disks REDOVOL1 through REDOVOL4).
- 3. In the ASM Configuration Assistant, on the **Create Disk Group** page, enter **RACDATA** for the **Disk Group Name**. In the **Redundancy** section, select **External (None)**. Click **OK**, and click **OK** again.
- On the Create Disk Group page, in the Select Member Disks section, select ORCL:DATAVOL1, ORCL:DATAVOL2, ORCL:DATAVOL3, and ORCL:DATAVOL4. Set the size of each to 300GB. Click OK.
- 5. On the **Create Disk Group** page, enter **RACREDO** for the **Disk Group Name**. In the **Redundancy** section, select **External (None)**. Click **OK**, and click **OK** again.
- On the Create Disk Group page, in the Select Member Disks section, select ORCL:REDOVOL1, ORCL:REDOVOL2, ORCL:REDOVOL3, and ORCL:REDOVOL4. Set the size of each to 64GB. Click OK.

11. Install and Create the Oracle Database 11gR2 RAC

To install and create the Oracle Database 11gR2 RAC

- 1. Log in into VMORARAC1 as oracle user and launch runInstaller from the Oracle software location to install the Oracle binaries.
- 2. In the Oracle Installer wizard, on the **Configure Security Updates** page, leave the **Email** field blank, and do not select **I wish to receive security updates via My Oracle Support**. Click **Next**.
- 3. On the Installation Option page, select Install database software only. Click Next.
- 4. On the **Grid Options** page, select **Real Application Clusters database installation**. Select the four nodes VMORARAC1, VMORARAC2, VMORARAC3, and VMORARAC4. Click **Next**.
- 5. On the Product Languages page, select English. Click Next.
- 6. On the Database Edition page, select Enterprise Edition (4.29GB). Click Next.
- 7. On the Installation Location page, enter /u01/app/oracle for Oracle Base, and /u01/app/oracle/product/11.2.0/dbhome_1 for Software Location. Click Next.
- 8. On the **Operating System Groups** page, select **dba** for the **Database Administrator (OSDBA) Group** and **oinstall** for the **Database Operator (OSOPER) Group**. Click **Next**.
- 9. Review the configuration on the **Summary** page, and click **Finish**.
- 10. After the installation is complete, open a terminal window, log in as root, and run the following script:
- 11. /u01/app/oracle/product/11.2.0/dbhome_1/root.sh

Repeat for each of the four nodes, and click OK.

- 11. On the Finish page, click Close.
- 12. Create the Oracle RAC database using Oracle Database Configuration Assistant (DBCA).

12. References

The following are resources and references for Oracle and VMware vSphere.

ESX Configuration Guide http://www.vmware.com/pdf/vsphere4/r41/vsp_41_esx_server_config.pdf

Guide to configure NTP on ESX servers http://kb.vmware.com/kb/1003063

Timekeeping in VMware Virtual Machines <u>http://www.vmware.com/files/pdf/Timekeeping-In-VirtualMachines.pdf</u>

Installing VMware Tools in a Linux virtual machine using Red Hat Package Manager (RPM) http://kb.vmware.com/kb/1018392

Oracle ASMLib http://www.oracle.com/technetwork/topics/linux/asmlib/index-101839.html

Oracle Database Oracle Clusterware and Oracle Real Application Clusters Installation Guide 10g Release 2 (10.2) for Linux http://download.oracle.com/docs/cd/B19306_01/install.102/b14203/toc.htm

Oracle Clusterware Installation Guide 11g Release 1 (11.1) for Linux http://www.oracle.com/pls/db111/to_toc?pathname=install.111/b28263/toc.htm

Oracle Real Application Clusters Installation Guide 11g Release 1 (11.1) for Linux and UNIX http://www.oracle.com/pls/db111/to_toc?pathname=install.111/b28264/toc.htm

13. Appendix A: Deployment of Oracle RAC with RDM

This section describes the following:

- Deployment steps for Four-Node Oracle RAC with RDM
- Virtual disk layout for RDMs.
- Adding CRS, DATA, and REDO RDMs to an Oracle RAC virtual machine.

13.1 Deployment Steps for Oracle RAC on vSphere with RDM

The following process diagram illustrates the deployment steps for deploying a four-node Oracle RAC on VMware vSphere 4.1 with RDM.



Figure 15. Deployment Steps for a Four-Node Oracle RAC on vSphere with RDM

13.2 Virtual Disk Layout

Table 1. Virtual Disk Layout

Oracle RAC on VMware vSphere Deployment Guide

Virtual Disk on ESX	Guest OS Device Name	Virtual Device	Virtual SCSI Driver	Size (GB)	Purpose
VMDK – Hard disk 1	/dev/sda	SCSI 0:0	LSI Logic	50	Oracle Enterprise Linux 5.5 OS and Oracle binaries
RDM – Hard disk 2	Shared disk /dev/sdb1	SCSI 1:0	Paravirtual	20	CRS and voting disk
RDM – Hard disk 3	Shared disk /dev/sdc1	SCSI 1:1	Paravirtual	20	CRS and voting disk
RDM – Hard disk 4	Shared disk /dev/sdd1	SCSI 1:2	Paravirtual	20	CRS and voting disk
RDM – Hard disk 5	Shared disk /dev/sde1	SCSI 1:3	Paravirtual	300	RAC database DATA
RDM – Hard disk 6	Shared disk /dev/sdf1	SCSI 1:4	Paravirtual	300	RAC database DATA
RDM – Hard disk 7	Shared disk /dev/sdg1	SCSI 1:5	Paravirtual	300	RAC database DATA
RDM – Hard disk 8	Shared disk /dev/sdh1	SCSI 1:6	Paravirtual	300	RAC database DATA
RDM – Hard disk 9	Shared disk /dev/sdi1	SCSI 1:8	Paravirtual	300	RAC database DATA
RDM – Hard disk 10	Shared disk /dev/sdj1	SCSI 1:9	Paravirtual	300	RAC database DATA
RDM – Hard disk 11	Shared disk /dev/sdk1	SCSI 1:10	Paravirtual	300	RAC database DATA
RDM – Hard disk 12	Shared disk /dev/sdl1	SCSI 1:11	Paravirtual	300	RAC database DATA
RDM – Hard disk 13	Shared disk /dev/sdm1	SCSI 1:12	Paravirtual	300	RAC database DATA
RDM – Hard disk 14	Shared disk /dev/sdn1	SCSI 1:13	Paravirtual	300	RAC database DATA
RDM – Hard disk 15	Shared disk /dev/sdo1	SCSI 2:0	Paravirtual	64	RAC database REDO

Virtual Disk on ESX	Guest OS Device Name	Virtual Device	Virtual SCSI Driver	Size (GB)	Purpose
RDM – Hard disk 16	Shared disk /dev/sdp1	SCSI 2:1	Paravirtual	64	RAC database REDO
RDM – Hard disk 17	Shared disk /dev/sdq1	SCSI 2:2	Paravirtual	64	RAC database REDO
RDM – Hard disk 18	Shared disk /dev/sdr1	SCSI 2:3	Paravirtual	64	RAC database REDO

13.3 Create a Virtual Machine

The section describes creation of the first virtual machine (that is the first RAC node) using the vSphere client. This is created on VMFS and corresponds to the root drive. Two NICs are assigned for the public and private networks. Three RDM LUNs are assigned to the virtual machine for CRS and voting. Only one LUN is required but three are used for redundancy

Four ESX hosts have been created and are visible in vCenter.

To create a new virtual machine

- 1. Log in to vCenter using the vSphere client.
- 2. Select a host and click **Create a new virtual machine** on the **Getting Started** tab.
- 3. In the Create New Virtual Machine wizard, select Typical for the Configuration, and click Next.
- 4. On the Name and Location page, enter VMORARAC1 for the Name, and click Next.
- 5. On the **Datastore** page, select **VMDATASTORE**, and click **Next**.
- 6. On the Guest Operating System page, select Linux from the Guest Operating System list. For the Version, select Oracle Linux 4/5 (64-bit) from the drop-down menu. Click Next.
- 7. On the Create a Disk page, set the Virtual Disk Size to 50GB, and click Next.
- 8. On the **Ready to Complete** page, select the **Edit the virtual machine settings before completion** check box. Click **Continue**.
- 9. On the Virtual Machine Properties page for the VMORARAC1 virtual machine, select 8 CPUs and 128GB Memory.
- 10. Click Finish.

13.4 Add CRS and Voting Disk

Three 20GB LUNs are attached to the virtual machine for RAC CRS and voting. Although only one is required, three are used for redundancy. With these LUNs:

- The LUNs are assigned as RDMs.
- The LUNs are attached to a SCSI controller configured as VMware Paravirtual.
- For the SCSI controller the SCSI BUS sharing policy is set to physical to allow these LUNs to be shared by multiple virtual machines on any ESX host.

The procedures in this section describe the steps needed to add RDMs for one virtual machine. Repeat all the steps in this section for each of the four virtual machines named VMORARAC1, VMORARAC2, VMORARAC3, and VMORARAC4.

To add one 20GB RDM for a virtual machine

- 1. In the vSphere client, select a virtual machine.
- 2. Right-click on the name of the virtual machine and select **Edit Settings** to display the **Virtual Machine Properties** pane.
- 3. Click Add to display the Add Hardware wizard.
- 4. In the Add Hardware wizard select Hard Disk for the Device Type, and click Next.
- 5. In the **Disk** section of the **Select a Disk** page, select **Raw Device Mappings**. Set the LUN size to **20GB**. Click **Next**.
- 6. On the Select Datastore page, in the Select datastore on which to store LUN mapping section, select Store with virtual machine. Click Next.
- 7. On the Compatibility Mode page, in the Compatibility section, select Physical. Click Next.
- 8. On the Advanced Options page, in the Virtual Device Node section, select SCSI (1:0). Click Next.
- 9. On the Ready to Complete page, click Finish.
- 10. Click OK.

To add a second 20GB RDM for the virtual machine

- 1. Select the virtual machine that was selected in the preceding step 1.
- 2. Repeat steps 2 through 7 in the preceding procedure to add one 20GB datastore.
- 3. On the Advanced Options page, in the Virtual Device Node section, select SCSI (1:1). Click Next.
- 4. Repeat steps 9 and 10 of the preceding procedure to add one 20GB datastore.

To add a third 20GB RDM for the virtual machine

- 1. Select the virtual machine that was selected in the preceding step 1.
- 2. Repeat steps 2 through 7 in the preceding procedure to add one 20GB datastore.
- 3. On the Advanced Options page, in the Virtual Device Node section, select SCSI (1:2). Click Next.
- 4. Repeat steps 9 and 10 of the preceding procedure to add one 20GB datastore.

Change the properties of the SCSI controller for the RDMs so they can be shared and configured as paravirtual.

To set the SCSI controller type to paravirtual

- 1. Select the virtual machine that was selected in the preceding step 1.
- 2. Right-click on the name of the virtual machine and select **Edit Settings** to display the **Virtual Machine Properties** pane.
- 3. In the device list, select SCSI controller 1.
- 4. In the SCSI Bus Sharing section, select Physical.
- 5. In the SCSI Controller Type section, click Change Type.
- 6. Select VMware Paravirtual.
- 7. Click **OK**, and click **OK** again.

The virtual machine properties can be viewed in vCenter, as seen in the following screenshot.

© 2011 VMware, Inc. All rights reserved.

Page 42 of 46

ardware Options Resources	
Show All Devices	Add Remove
ardware	Summary
Memory	131072 MB
CPUs	8
📃 Video card	Video card
VMCI device	Restricted
SCSI controller 0	LSI Logic Parallel
 VMCI device SCSI controller 0 SCSI controller 1 SCSI controller 2 	Paravirtual
SCSI controller 2	Paravirtual
Hard disk 1	Virtual Disk
遭 🛛 Hard disk 2	Mapped Raw LUN
避 🛛 Hard disk 3	Mapped Raw LUN
避 🛛 Hard disk 4	Mapped Raw LUN
避 🛛 Hard disk 5	Mapped Raw LUN
避 🛛 Hard disk 6	Mapped Raw LUN
🙄 Hard disk 7	Mapped Raw LUN
避 🛛 Hard disk 8	Mapped Raw LUN
避 🛛 Hard disk 9	Mapped Raw LUN
避 🛛 Hard disk 10	Mapped Raw LUN
避 🛛 Hard disk 11	Mapped Raw LUN
避 🛛 Hard disk 12	Mapped Raw LUN
避 🛛 Hard disk 13	Mapped Raw LUN
🙄 🛛 Hard disk 14	Mapped Raw LUN
Hard disk 15	Mapped Raw LUN
避 🛛 Hard disk 16	Mapped Raw LUN
遭 🛛 Hard disk 17	Mapped Raw LUN
避 🛛 Hard disk 18	Mapped Raw LUN
CD/DVD Drive 1	[] /vmimages/tools-iso
Network adapter 1	Oracle Public
😰 Network adapter 2	Oracle Private

Figure 16. First Virtual Machine RAC Node Hardware Devices

13.5 Add DATA and REDO Disks to Virtual Machine RAC Nodes

In this section, the database disks for data and redo logs are added to the virtual machine RAC nodes. The general procedure is:

- Data and redo LUNs are added to virtual machine VMORARAC1 as RDMs. This creates RDM mapping files in the VMFS datastore. The SCSI controller type is set to VMware Paravirtual.
- The same data and redo LUNs are added to the remaining three nodes (VMORARAC2, VMORARAC2, and VMORARAC3) by selecting the same RDM mappings created in the previous step. Again, the SCSI controller type is set to VMware Paravirtual.

To add DATA or REDO LUNs to the first virtual machine, VMORARAC1

- 1. In the vSphere client, select the virtual machine, VMORARAC1.
- 2. Right-click on the name of the virtual machine and select **Edit Settings** to display the **Virtual Machine Properties** pane.
- 3. Click Add to display the Add Hardware wizard.
- 4. In the Add Hardware wizard select Raw Device Mappings for the Device Type, and click Next.
- 5. In the Select a target LUN section of the Select a Disk page, select a 300GB LUN for DATA or a 64GB LUN for REDO. Click Next.
- 6. On the Select Datastore page, in the Select datastore on which to store LUN mapping section, select Store with virtual machine. Click Next.
- 7. On the Compatibility Mode page, in the Compatibility section, select Physical. Click Next.
- 8. On the Advanced Options page, in the Virtual Device Node section, select SCSI (1:3) for DATA, or SCSI (2:0) for REDO. Click Next.
- 9. On the Ready to Complete page, click Finish.
- 10. Click OK.
- 11. Repeat steps 1 through 7 for all the DATA and REDO LUNs. Change step 8 to use SCSI (1:4) for the next DATA LUN, or SCSI (2:1) for the next REDO LUN. For additional DATA or REDO LUNs, repeat steps 1 through 7 and continue the numbering sequence in step 8. For example, the third DATA LUN uses the numbering SCSI (1:5), and the third REDO LUN uses the numbering SCSI (2:2).

To set the SCSI controller type for the RDM LUNs to paravirtual

- 1. Select the virtual machine VMORARAC1.
- 2. Right-click on the name of the virtual machine and select **Edit Settings** to display the **Virtual Machine Properties** pane.
- 3. In the device list, select SCSI controller 1.
- 4. In the SCSI Controller Type section, click Change Type.
- 5. Select VMware Paravirtual.
- 6. Click **OK**, and click **OK** again.

To add DATA or REDO LUNs to the remaining virtual machines

- 1. In the vSphere client, select a virtual machine (VMORARAC2, VMORARAC3, or VMORARAC4).
- 2. Right-click on the name of the virtual machine and select **Edit Settings** to display the **Virtual Machine Properties** pane.
- 3. Click Add to display the Add Hardware wizard.

© 2011 VMware, Inc. All rights reserved.

- 4. In the Add Hardware wizard select Hard Disk for the Device Type, and click Next.
- 5. In the Select the type of disk to use section of the Select a Disk page, select Use an existing virtual disk. Click Next.
- 6. On the **Select Existing Disk** page, in the **Disk File Path** section, select the path to the vmdk pointer file for the LUN. Click **Next**.
- 7. On the **Compatibility Mode** page, click **Next**.
- 8. On the Advanced Options page, in the Virtual Device Node section, select SCSI (1:3) for DATA, or SCSI (2:0) for REDO. Set the Mode to Independent and Persistent. Click Next.
- 9. On the Ready to Complete page, click Finish.
- 10. Click **OK**.
- 11. Repeat steps 1 through 7 for all the DATA and REDO LUNs. Change step 8 to use SCSI (1:4) for the next DATA LUN, or SCSI (2:1) for the next REDO LUN. For additional DATA or REDO LUNs, repeat steps 1 through 7 and continue the numbering sequence in step 8. For example, the third DATA LUN uses the numbering SCSI (1:5), and the third REDO LUN uses the numbering SCSI (2:2).
- 12. Repeat steps 1 through 11 for each of the other virtual machines (VMORARAC2, VMORARAC3, or VMORARAC4).

To set the SCSI controller type for the RDM LUNs to paravirtual

- 1. Select a virtual machine (VMORARAC2, VMORARAC3, or VMORARAC4).
- 2. Right-click on the name of the virtual machine and select **Edit Settings** to display the **Virtual Machine Properties** pane.
- 3. In the device list, select SCSI controller 1.
- 4. In the SCSI Controller Type section, click Change Type.
- 5. Select VMware Paravirtual.
- 6. Click OK, and click OK again.

To format disks using the Linux fdisk utility

- 1. Follow the steps in Section 6.4 to format one disk.
- 2. Repeat, using fdisk to format each disk.

The devices for the virtual machine should look like the following screenshot.

Figure 17. Virtual Machine RAC Node with All Attached Hardware Devices (Ind	cludes All Disks)
---	-------------------

ardware Options Resources		Virtual Machine	Version:
1 · · · ·		Memory Configuration	
Show All Devices	Add Remove	255 GB ┥ Memory Size: 128 🚍 🖸	в
Hardware	Summary		
Memory	131072 MB	128 GB Maximum recommended for this guest OS: 255 GB.	
🔲 CPUs	8	Marine and a feature	
📃 Video card	Video card	64 GB Maximum recommended for best	
VMCI device	Restricted	Default recommended for this	
SCSI controller 0	LSI Logic Parallel	32 GB guest OS; 384 MB.	
SCSI controller 1	Paravirtual	Minimum recommended for this	
SCSI controller 2	Paravirtual	16 GB guest OS: 256 MB.	
😅 🛛 Hard disk 1	Virtual Disk	0.00	
😅 🛛 Hard disk 2	Mapped Raw LUN	8 GB -	
😅 🛛 Hard disk 3	Mapped Raw LUN	4 GB	
📟 🛛 Hard disk 4	Mapped Raw LUN	4 GD	
📟 🛛 Hard disk 5	Mapped Raw LUN	2 GB	
😅 🛛 Hard disk 6	Mapped Raw LUN		
😅 🛛 Hard disk 7	Mapped Raw LUN	1 GB -	
😅 🛛 Hard disk 8	Mapped Raw LUN	1 GD	
😅 Hard disk 9	Mapped Raw LUN	512 MB	
😅 🛛 Hard disk 10	Mapped Raw LUN		
😅 🛛 Hard disk 11	Mapped Raw LUN	256 MB	
😅 🛛 Hard disk 12	Mapped Raw LUN		
😅 🛛 Hard disk 13	Mapped Raw LUN	128 MB	
😅 🛛 Hard disk 14	Mapped Raw LUN		
Hard disk 15	Mapped Raw LUN	64 MB	
🚍 Hard disk 16	Mapped Raw LUN		
Hard disk 17	Mapped Raw LUN	32 MB	
Hard disk 18	Mapped Raw LUN		
CD/DVD Drive 1	[] /vmimages/tools-iso	16 MB	
😨 Network adapter 1	Oracle Public		
😨 Network adapter 2	Oracle Private	8 MB -	
		4 MB	
Help		OKCa	ancel